



## How to run PRUX Daemon on Windows 10, live PRUX CORE Node.


1. PRUX-Coin Wallet Core get it from Main Source : <https://prux.info>
2. Search Download for WIN10 and Download prux-qt.exe
3. After Download, Create on Desktop a folder PRUX.




4. Move prux.exe from Download Folder to new PRUX Folder on Desktop
5. Go to PRUX Folder on Desktop and click on prux.exe
6. Click More info and let`s run prux.exe.




7. Wait, PRUX Daemon will start. 0 Node`s Connected, nothing happen, close PRUX-Wallet




## 8. Go to Windows Explorer




## 9. Go to C:\Users\YourUsername (YourUsername, should be replaced with your username)



## 10. Set in addressbar C:\Users\YourUsername\appdata and ENTER



## 11. Click Roaming and open folder prux



## 12. First Disable the Hide extensions for known file types Win10


### Show File Extensions in Windows 10

There are two ways how you can go about accessing this setting. One way is through the Control Panel, and another way is through Windows Explorer itself. In both ways, you will be toggling the option to see file extensions.

#### 1] Through Folder Options

Open Control Panel > Appearance and Personalization. Now, click on **Folder Options** or **File Explorer Option**, as it is now called > View tab. In this tab, under Advanced Settings, you will see the option **Hide extensions for known file types**. Uncheck this option and click on Apply and OK.


Windows 10 users may also search for File Explorer Options in Start search box and open this box.




Now, you can see file extensions for all files anywhere on your Windows system.

<https://www.thewindowsclub.com/show-file-extensions-in-windows>

13. Click right mouse button and create a empty textfile and call it prux.conf.  
Attention: without (.txt) at the end should be only prux.conf !



14. Should look like that!



**15. Open and edit the new crated prux.conf with follow content:**

```
server=1
daemon=1
rpcuser=yourchoicercuser
rpcpassword=yourchoicepassword
rpcport=8933
port=9595
maxconnections=15
addnode=mastermining.net
addnode=xvg.mastermining.net
addnode=prux.info
addnode=seed.prux.info
```

**16. Replace rpcuser=yourchoicercuser**


Enter some new random username (Don't use your real name and don't win)

Example -> `rpcuser=JohnMcLoggle+74xH`

**17. Change rpcpassword=yourchoicepassword**


Enter some new random characters

Example -> `rpcpassword=HCh+zgFj7Fdfr38FSu2+ffdFffez65`

**18. Now it should look like that. Save that file and close Editor!**

```
prux.conf - Editor
Datei Bearbeiten Format Ansicht Hilfe
server=1
daemon=1
rpcuser=JohnMcLoggle+74xH
rpcpassword=HCh+zgFj7Fdfr38FSu2+ffdFffez65
rpcport=8933
port=9595
maxconnections=15
addnode=mastermining.net
addnode=xvg.mastermining.net
addnode=prux.info
addnode=seed.prux.info
Ze 6, Sp 10 100% Windows (CRLF) UTF-8
```

19. Now, go back to Windows Desktop and open Folder PRUX and start PRUX Wallet, PRUX CORE NODE with Double Click on prux.exe



*PRUX synchronization process is running/started. You need minimum 1 peer connected. The synchronization process could take a couple of days to complete.*